

**Honeywell**

# AdproXO Client USER GUIDE

Provided By:




**ENVERA®**  
NEXT GENERATION SECURITY

# View Live Video


A shortcut to AdproXO Client has been placed on your “desktop” screen. Double click the icon to launch the application.




A Login window will pop up. Highlight your community and click **Connect**.



A black screen will appear and the **Live Video** tab will be selected. To view live video, click the camera number(s) that are not greyed out in the **Cameras** section.



The live video for each selected camera will load. To stop viewing a particular camera, simply click its camera number in the **Cameras** section again.



To **Zoom In** on a particular image, click on camera image of interest and your mouse pointer will turn into a magnifying glass. Click the mouse again and hold for it to zoom in. To **Zoom Out**, hold the Shift button, click and hold the mouse button. If your mouse has a wheel you can use this to zoom in and out.

### **Capturing Live Images & Recordings**

You can capture the live image or video from an individual camera or all cameras, by using the options in the **Tools** section.


#### ***Take a Snapshot***

To take a Snapshot of a live image, click on camera image of interest. A red box around the frame indicates that camera has been selected. Then click **Snapshot** in the **Tools** section. To take a Snapshot of all camera images at a specific moment, click **All** in the **Tools** section.






**Tools Section**



**Individual Camera Snapshot**



**Multiple Camera Snapshots**


### Record Live Video

You will repeat the same initial steps as if you were taking an individual Snapshot; however, you will click **Record** in the **Tools** section. To record live video from all cameras at a specific moment, click **All** in the **Tools** section.



**Tools Section**

The Browse for Folder window will appear, allowing you to create or select the folder where you wish to save your recording(s). Click **OK** when you are done.



The video will continue to record until you click the **Record** or **All** button a second time to stop recording. You can then retrieve the video in the folder you previously selected as the location to save the files.

0001 - CoralBaySouth

Organize Include in library Share with Burn New folder

**Favorites**

- Desktop
- Downloads
- Recent Places

**Libraries**

- Documents
- Music
- Pictures
- Videos

**Computer**


- Local Disk (C:)
- COMPANY (\\ENV-FS1) (S:)
- DOCUMENTS (\\ENV-FS1) (X:)
- Envera Operations (\\192.168.1.10) (Z:)

**Network**


Name	Date modified	Type	Size
01 - Camera 1 - 12-03-30 10-35-22	3/30/2012 10:35 AM	HBOX File	300 KB
01 - Camera 1 - 12-03-30 10-37-03	3/30/2012 10:37 AM	HBOX File	473 KB
02 - Camera 2 - 12-03-30 10-37-04	3/30/2012 10:37 AM	HBOX File	438 KB
03 - Camera 3 - 12-03-30 10-37-04	3/30/2012 10:37 AM	HBOX File	462 KB
04 - Camera 4 - 12-03-30 10-37-04	3/30/2012 10:37 AM	HBOX File	452 KB
05 - Camera 5 - 12-03-30 10-37-04	3/30/2012 10:37 AM	HBOX File	195 KB

# Review Recorded Video

To review recorded video, click the **Recorded video** tab at the top of the window. Camera 1 will be displayed in the Recorded video area and **By Time** will be selected as the default filter.




The view at the bottom of the screen will default to the **Timeline** view which is the view you will want to utilize. At the top of the Timeline area, you will see that the current day, month and year are being displayed. In the timeline itself the gold color indicates continuous recording and the red indicates motion recordings.




## Search Recorded Video 'By Time'

To perform a video search By Time, follow these steps:

1. Place a check in the box next to each camera from which you would like to review the video.
2. Use the arrows to scroll to the month of interest and then choose the date/day of interest.
3. Drag the black line to the time at which point you would like to start reviewing video or set the time brackets around the time period of interest.
4. Click the **Play** button.




### Continuous Recording



### Motion Recording

A review pane with all selected cameras will display and the recorded video will begin to play. You can use the video controls in the bottom left-hand corner to pause, rewind or fast forward as you review the recorded video. To exit the review pane simply click the **Stop** button.



## Search Recorded Video 'By Event'

You can also download recorded video clips **By Event** following these steps:

1. Select the filter **By Event** in the upper right-hand corner of the Recorded video window.
2. In the row of the particular camera of interest, drag the black line to the time of interest. A list of events (+/- 150 seconds of the selected time) will display.
3. Select the event of interest and click **Download or double the event**. After it is done downloading, the clip will begin to play in the Recorded video area.

